

FILEID**BASPOWDR

BBBBBBBB	AAAAAA	SSSSSSSS	PPPPPPPP	000000	WW	WW	DDDDDDDD	RRRRRRRR	
BBBBBBBB	AAAAAA	SSSSSSSS	PPPPPPPP	000000	WW	WW	DDDDDDDD	RRRRRRRR	
BB	BB	AA	AA	SS	PP	PP	00	RR	RR
BB	BB	AA	AA	SS	PP	PP	00	RR	RR
BB	BB	AA	AA	SS	PP	PP	00	RR	RR
BB	BB	AA	AA	SS	PP	PP	00	RR	RR
BBBBBBBB	AA	AA	AA	SSSSSS	PPPPPPPP	00	WW	DD	RRRRRRRR
BBBBBBBB	AA	AA	AA	SSSSSS	PPPPPPPP	00	WW	DD	RRRRRRRR
BB	BB	AAAAAA	AA	SS	PP	00	WW	DD	RR RR
BB	BB	AAAAAA	AA	SS	PP	00	WW	DD	RR RR
BB	BB	AA	AA	SS	PP	00	WWWW	DD	RR RR
BB	BB	AA	AA	SS	PP	00	WWWW	DD	RR RR
BBBBBBBB	AA	AA	AA	SSSSSSSS	PP	000000	WW	DDDDDDDD	RR RR
BBBBBBBB	AA	AA	AA	SSSSSSSS	PP	000000	WW	DDDDDDDD	RR RR

LL	IIIIII	SSSSSSSS
LL	IIIIII	SSSSSSSS
LL	II	SS
LLLLLLLL	IIIIII	SSSSSSSS
LLLLLLLL	IIIIII	SSSSSSSS

BASSPOWDR
Table of contents

; BASIC double ** float routine

L 10

15-SEP-1984 23:59:02 VAX/VMS Macro V04-00

Page 0

(2) 46 DECLARATIONS
(3) 83 BASSPOWDR - BASIC double ** float

```
0000 1 .TITLE BASSPOWDR
0000 2 .IDENT /1-001/
0000 3
0000 4
0000 5 ****
0000 6 *
0000 7 * COPYRIGHT (c) 1978, 1980, 1982, 1984 BY
0000 8 * DIGITAL EQUIPMENT CORPORATION, MAYNARD, MASSACHUSETTS.
0000 9 * ALL RIGHTS RESERVED.
0000 10 *
0000 11 * THIS SOFTWARE IS FURNISHED UNDER A LICENSE AND MAY BE USED AND COPIED
0000 12 * ONLY IN ACCORDANCE WITH THE TERMS OF SUCH LICENSE AND WITH THE
0000 13 * INCLUSION OF THE ABOVE COPYRIGHT NOTICE. THIS SOFTWARE OR ANY OTHER
0000 14 * COPIES THEREOF MAY NOT BE PROVIDED OR OTHERWISE MADE AVAILABLE TO ANY
0000 15 * OTHER PERSON. NO TITLE TO AND OWNERSHIP OF THE SOFTWARE IS HEREBY
0000 16 * TRANSFERRED.
0000 17 *
0000 18 * THE INFORMATION IN THIS SOFTWARE IS SUBJECT TO CHANGE WITHOUT NOTICE
0000 19 * AND SHOULD NOT BE CONSTRUED AS A COMMITMENT BY DIGITAL EQUIPMENT
0000 20 * CORPORATION.
0000 21 *
0000 22 * DIGITAL ASSUMES NO RESPONSIBILITY FOR THE USE OR RELIABILITY OF ITS
0000 23 * SOFTWARE ON EQUIPMENT WHICH IS NOT SUPPLIED BY DIGITAL.
0000 24 *
0000 25 *
0000 26 ****
0000 27 :
0000 28 :
0000 29 ++
0000 30 : FACILITY: Basic Support Library
0000 31 :
0000 32 : ABSTRACT:
0000 33 :
0000 34 : This module contains entry points to support exponentiation
0000 35 : (** or ^) in BASIC-PLUS-2 for DOUBLE ** FLOAT.
0000 36 :
0000 37 : ENVIRONMENT: User Mode, AST Reentrant
0000 38 :
0000 39 :--
0000 40 : AUTHOR: P. Levesque , CREATION DATE: 5-Oct-81
0000 41 :
0000 42 : MODIFIED BY:
0000 43 :
0000 44 : 1-001 - Original
```

```
0000 46      .SBTTL DECLARATIONS
0000 47      :
0000 48      : INCLUDE FILES:
0000 49      :
0000 50      :
0000 51      :
0000 52      : EXTERNAL DECLARATIONS:
0000 53      :
0000 54      .DSABL GBL          ; Prevent undeclared
0000 55          ; symbols from being
0000 56          ; automatically global.
0000 57          :
0000 58      .EXTRN OTSS$POWDR    ; OTSS double ** float exponentiation
0000 59      .EXTRN OTSS$POWDJ    ; OTSS double ** int exponentiation
0000 60      .EXTRN BASS$K-DIVBY_ZER ; Divide by Zero
0000 61      .EXTRN BASS$K-ILLARGLOG ; Illegal argument in LOG
0000 62      .EXTRN BASS$$STOP      ; Error reporting routine
0000 63          :
0000 64      :
0000 65      : MACROS:
0000 66      :
0000 67      :
0000 68      :
0000 69      : EQUATED SYMBOLS:
0000 70      :
0000 71      :
0000 72      :
0000 73      : OWN STORAGE:
0000 74      :
0000 75      :
0000 76      :
0000 77      : PSECT DECLARATIONS:
0000 78      :
0000000000 79      .PSECT _BASS$CODE PIC, USR, CON, REL, LCL, SHR, -
0000          80          EXE, RD, NOWRT, LONG
0000          81          :
```

0000 83 .SBTTL BASSPOWDR - BASIC double ** float

0000 84 :++
0000 85 : FUNCTIONAL DESCRIPTION:0000 87 : This routine takes BASE ** EXP, using the following table
0000 88 : for unusual cases:0000 89 :
0000 90 : BASE > 0 Call OTSSPOWDR, normal case.
0000 91 : BASE = 0, EXP > 0 Return 0.0.
0000 92 : BASE = 0, EXP = 0 Return 1.0.
0000 93 : BASE = 0, EXP < 0 Error: divide by zero
0000 94 : BASE < 0, EXP even integer Call OTSSPOWDJ with -BASE
0000 95 : BASE < 0, EXP odd integer Call OTSSPOWDJ with -BASE, negate result
0000 96 : BASE < 0, EXP not integer Error: illegal argument in LOG.
0000 97 :
0000 98 : CALLING SEQUENCE:
0000 99 :
0000 100 : CALL result.wd.v = BASSPOWDR (base.rd.v, exponent.rf.v)
0000 101 :
0000 102 : INPUT PARAMETERS:
0000 103 :
0000 104 : base = 4
0000 105 : exponent = 12
0000 106 :
0000 107 : IMPLICIT INPUTS:
0000 108 :
0000 109 : NONE
0000 110 :
0000 111 : OUTPUT PARAMETERS:
0000 112 :
0000 113 : NONE
0000 114 :
0000 115 : IMPLICIT OUTPUTS:
0000 116 :
0000 117 : NONE
0000 118 :
0000 119 : FUNCTION VALUE:
0000 120 : COMPLETION CODES:
0000 121 :
0000 122 : double result of exponentiation
0000 123 :
0000 124 : SIDE EFFECTS:
0000 125 :
0000 126 : Will signal Divide By Zero or Illegal argument in LOG if its
0000 127 : arguments are bad, and OTSSPOWDR and OTSSPOWDJ may also signal.
0000 128 :
0000 129 :--
0000 130 :
0000 131 BASSPOWDR:: .MASK OTSSPOWDR : Entry point
0002 132 : Since this routine uses no
0002 133 : registers and usually transfers
0002 134 : control to OTSSPOWDR, we copy
0002 135 : its register save mask and then
0002 136 : JMP past its save mask and only
0002 137 : save the registers once
0002 138 : Test base relationship to zero
0002 139 : If base leq 0, do case analysis04 AC 73 0002 138 TSTD base(AP)
06 15 0005 139 BLEQ 1\$

00000002'GF 17 0007 140 JMP G^OTSSPOWDR+2 ; Transfer control to the OTSS
0000D 141 ; routine to do exponentiation
0000D 142 :+
0000D 143 : Come here if the base is less than or equal to zero. We must filter
0000D 144 : several special cases, as described above.
0000D 145 :-
50 50 08 00 0C 2E 13 000D 146 :\$: BEQL 4\$; Branch if base = 0
AC 1A 54 000F 147 EMODF exponent(AP), #0, #1, R0, R0
12 0016 148 BNEQ 3\$; Branch if exponent is not integer
0018 149 :+
0018 150 : The base is less than zero and the exponent is an integer.
0018 151 : BASIC defines this as working the same way as if an integer was
0018 152 : in the expression (making a floating variable which happens to
0018 153 : contain an integer value equivalent to an integer variable).
0018 154 :-
50 0C AC 4A 0018 155 CVTFL exponent(AP), R0 ; Convert exponent to integer
50 DD 001C 156 PUSHL R0 ; Save for even/odd test
50 DD 001E 157 PUSHL R0 ; Stack as parameter to OTSSPOWDJ
7E 04 AC 72 0020 158 MNEG D base(AP), -(SP) ; Stack -base also
00000000'GF 03 FB 0024 159 CALLS #3, G^OTSSPOWDJ ; Call integer power routines
03 8E E9 002B 160 BLBC (SP)+ 2\$; Branch if exponent even
50 50 72 002E 161 MNEG D R0, R0 ; Exponent odd, negate the result
04 0031 162 2\$: RET ; and return with it.
0032 163 :+
0032 164 : Come here if the base is less than zero but the exponent is not
0032 165 : an integer. BASIC defines this as an error.
0032 166 :-
7E 00'BF 9A 0032 167 3\$: MOVZBL #BASSK ILLARGLOG, -(SP) ; Illegal Argument in LOG
00000000'GF 01 FB 0036 168 CALLS #1, G^BASS\$STOP ; Never return.
003D 169 :+
003D 170 : Come here if the base is equal to zero. The value we return depends
003D 171 : upon the sign of the exponent.
003D 172 :-
0C AC 53 003D 173 4\$: TSTF exponent(AP) ; Test the exponent against zero
09 19 0040 174 BLSS 6\$; Branch if exponent less 0
03 13 0042 175 BEQL 5\$; Branch if exponent is 0
0044 176 :+
0044 177 : Come here if the base is zero and the exponent is greater than zero.
0044 178 : BASIC defines this as 0.0.
0044 179 :-
50 7C 0044 180 CLRD R0 ; R0, R1 = 0.0
04 0046 181 RET ; Return to caller
0047 182 :+
0047 183 : Come here if the base is zero and the exponent is zero. BASIC defines
0047 184 : this as 1.0.
0047 185 :-
50 08 70 0047 186 5\$: MOVD #1, R0 ; R0, R1 = 1.0
04 004A 187 RET ; Return to caller.
004B 188 :+
004B 189 : Come here if the base is zero and the exponent is less than zero.
004B 190 : BASIC defines this as an error.
004B 191 :-
7E 00'BF 9A 004B 192 6\$: MOVZBL #BASSK DIVBY ZER, -(SP) ; Divide by zero
00000000'GF 01 FB 004F 193 CALLS #1, G^BASS\$STOP ; Report error, never return.
0056 194 :
0056 195 .END

BAS\$POWDR
Symbol table

: BASIC double ** float routine

BAS\$STOP	*****	X	00
BAS\$DIVBY_ZER	*****	X	00
BAS\$K_ILLARGLOG	*****	X	00
BAS\$POWDR	00000000	RG	01
BASE	=	00000004	
EXPONENT	=	0000000C	
OTSSPOWDJ	*****	X	00
OTSSPOWDR	*****	X	00

```
! Psect synopsis !
-----
```

PSECT name	Allocation	PSECT No.	Attributes	CON	ABS	LCL	NOSHR	NOEXE	NORD	NOWRT	NOVEC	BYTE
. ABS	00000000	(0.)	00 (0.)	NOPIC	USR	CON	REL	LCL	NOSHR	NOEXE	NORD	NOWRT
_BASSCODE	00000056	(86.)	01 (1.)	PIC	USR	CON		LCL	SHR	EXE	RD	NOVEC LONG

```
! Performance indicators !
-----
```

Phase	Page faults	CPU Time	Elapsed Time
Initialization	29	00:00:00.07	00:00:00.40
Command processing	104	00:00:00.43	00:00:01.94
Pass 1	72	00:00:00.46	00:00:01.45
Symbol table sort	0	00:00:00.01	00:00:00.01
Pass 2	47	00:00:00.38	00:00:01.08
Symbol table output	3	00:00:00.01	00:00:00.01
Psect synopsis output	2	00:00:00.02	00:00:00.07
Cross-reference output	0	00:00:00.00	00:00:00.00
Assembler run totals	259	00:00:01.39	00:00:04.96

The working set limit was 900 pages.

2216 bytes (5 pages) of virtual memory were used to buffer the intermediate code.

There were 10 pages of symbol table space allocated to hold 8 non-local and 6 local symbols.

195 source lines were read in Pass 1, producing 8 object records in Pass 2.

0 pages of virtual memory were used to define 0 macros.

```
! Macro library statistics !
-----
```

Macro library name

\$_255\$DUA28:[SYSLIB]STARLET.MLB:2

Macros defined

0

0 GETS were required to define 0 macros.

There were no errors, warnings or information messages.

MACRO/ENABLE=SUPPRESSION/DISABLE=(GLOBAL,TRACEBACK)/LIS=LIS\$:BASPOWDR/OBJ=OBJ\$:BASPOWDR MSRC\$:BASPOWDR/UPDATE=(ENH\$:BASPOWDR)

0029 AH-BT13A-SE
VAX/VMS V4.0

DIGITAL EQUIPMENT CORPORATION
CONFIDENTIAL AND PROPRIETARY

BASOPEN

BASPOS
LIS

BASPOWD
LIS

BASPOWG
LIS

BASPOWH
LIS

BASPOWR
LIS

BASPURTOB
LIS

BASPOWD
LIS

BASOPENZ
LIS

BASPOWR
LIS

BASPOWG
LIS

BASPOWD
LIS

BASPOWR
LIS

BASPOWH
LIS